

# Sentinel RMS SDK v9.1.0

Linux (32 and 64-bit) Release Notes

## Disclaimer and Copyrights

All information herein is either public information or is the property of and owned solely by Gemalto NV. and/or its subsidiaries who shall have and keep the sole right to file patent applications or any other kind of intellectual property protection in connection with such information.

Nothing herein shall be construed as implying or granting to you any rights, by license, grant or otherwise, under any intellectual and/or industrial property rights of or concerning any of Gemalto's information.

This document can be used for informational, non-commercial, internal and personal use only provided that:

- The copyright notice below, the confidentiality and proprietary legend and this full warning notice appear in all copies.
- This document shall not be posted on any network computer or broadcast in any media and no modification of any part of this document shall be made.

Use for any other purpose is expressly prohibited and may result in severe civil and criminal liabilities.

The information contained in this document is provided "AS IS" without any warranty of any kind. Unless otherwise expressly agreed in writing, Gemalto makes no warranty as to the value or accuracy of information contained herein.

The document could include technical inaccuracies or typographical errors. Changes are periodically added to the information herein. Furthermore, Gemalto reserves the right to make any change or improvement in the specifications data, information, and the like described herein, at any time.

Gemalto hereby disclaims all warranties and conditions with regard to the information contained herein, including all implied warranties of merchantability, fitness for a particular purpose, title and non-infringement. In no event shall Gemalto be liable, whether in contract, tort or otherwise, for any indirect, special or consequential damages or any damages whatsoever including but not limited to damages resulting from loss of use, data, profits, revenues, or customers, arising out of or in connection with the use or performance of information contained in this document.

Gemalto does not and shall not warrant that this product will be resistant to all possible attacks and shall not incur, and disclaims, any liability in this respect. Even if each product is compliant with current security standards in force on the date of their design, security mechanisms' resistance necessarily evolves according to the state of the art in security and notably under the emergence of new attacks. Under no circumstances, shall Gemalto be held liable for any third party actions and in particular in case of any successful attack against systems or equipment incorporating Gemalto products.

Gemalto disclaims any liability with respect to security for direct, indirect, incidental or consequential damages that result from any use of its products. It is further stressed that independent testing and verification by the person using the product is particularly encouraged, especially in any application in which defective, incorrect or insecure functioning could result in damage to persons or property, denial of service or loss of privacy.

© 1994 - 2016 Gemalto NV. All rights reserved. Gemalto, the Gemalto logo, are trademarks and service marks of Gemalto and are registered in certain countries.

Sentinel® RMS makes use of certain third-party softwares. Please refer to SentinelRMSAcknowledgements document for more information about third-party softwares used by Sentinel® RMS.

**Product Version:** 9.1.0

**Document Number:** 007-013330-001, Revision B

**Release Date:** August 2016

# Contents

<b>Sentinel RMS SDK v9.1.0 for Linux (32 and 64-bit) - Release Notes</b> .....	<b>6</b>
About This Document .....	6
Product Overview .....	6
What's New in Sentinel RMS SDK v9.1.0? .....	7
Unified API Enhancements .....	7
Added New Attributes in the sntl_licensing_app_context_new API .....	7
sntl_licensing_get_info API Enhancements .....	7
Enhancement in the sntl_licensing_get_session_info API .....	9
Renaming of Attribute Key Names .....	9
Traditional API Enhancements .....	10
Obtaining the Start and Expiration Time of a Checked-out Commuter License .....	10
Licenses with Entitlement Start and Expiration Time .....	10
New Fields in the CodeT (License), VLSfeatureInfo and VLSlicenseInfo structures .....	10
License Version Upgraded to v17 .....	10
Enhancements in the Java Interface for Unified API .....	11
Miscellaneous Changes .....	11
Increased Size of Vendor Usage Data .....	11
Documentation Changes .....	11
What's New in the SCL Add-on for RMS? .....	12
Problems Corrected in This Release .....	13
Installation Information .....	14
Before You Install... .....	15
Administrator Privileges .....	15
RMS SDK Serial Number .....	15
System Requirements .....	16
Installation Instructions .....	18
Installing Sentinel UNIX Driver (SUD) .....	18
Installed Directories .....	20
Major Documentation Resources .....	21
Developer's Guide .....	21
API Reference Guide .....	21
System Administrator's Guide .....	21
License Generation API Reference Guide .....	21
SCL Add on for RMS Documentation .....	22
Technical Support .....	23



# Sentinel RMS SDK v9.1.0 for Linux (32 and 64-bit) - Release Notes

## About This Document

---

This document contains details about the new features and installation of the Sentinel RMS v9.1.0 for Linux. This release includes feature changes and problem fixes since the last major release v9.0.0.

## Product Overview

---

Sentinel RMS is a software licensing SDK for your applications. It increases revenue by authorizing the use of your applications and offers a variety of licensing schemes to boost your product sales. It also provides tools that system administrators can use to track and manage licenses in a network.

When SCL add-on is combined with the license enforcement features of Sentinel RMS and the licensing management features of Sentinel EMS, it makes a complete solution that provides the benefits of cloud-connected licensing to applications deployed in customer's network or hosted online. Usage collection and reporting is the most significant advantage obtained with cloud-connected licensing.

## What's New in Sentinel RMS SDK v9.1.0?

This section provides details about the new features and enhancements included in the RMS v9.1 release:

### Unified API Enhancements

The following major enhancements, related to the Unified API, are included in this release. For more information, refer to the chapter "Unified API" of the Sentinel RMS SDK API Reference Guide:

#### *Added New Attributes in the `sntl_licensing_app_context_new` API*

In this release, the following attributes are added to the `sntl_licensing_app_context_new` API:

Attribute Key	Purpose
<code>SNTL_ATTR_APPCONTEXT_DEFAULT_ERROR_HANDLER</code>	Sets the default error handler for troubleshooting error conditions.
<code>SNTL_ATTR_APPCONTEXT_TRACE_LEVEL</code>	Sets the tracing of the various licensing operations.
<code>SNTL_ATTR_APPCONTEXT_SERVER_PORT</code>	Sets a network port, different from the default, for communicating with the License Manager.
<code>SNTL_ATTR_APPCONTEXT_BROADCAST_INTERVAL</code>	Sets the timeout interval (in seconds) to find a License Manager in the subnet.
<code>SNTL_ATTR_APPCONTEXT_AUTO_REFRESH</code>	Defines the behavior of the automatic license refresh.
<code>SNTL_ATTR_APPCONTEXT_XDISPLAYNAME</code>	Sets the name of the X display where the user needs to display the application.
<code>SNTL_ATTR_APPCONTEXT_VENDOR_DEFINED_SHARINGID</code>	Sets the special vendor-defined ID that can be used for license sharing decisions.

#### *`sntl_licensing_get_info` API Enhancements*

This section briefly describes the various enhancements done in the `sntl_licensing_get_info` API:

#### *Added New Query Types*

In this release, the `sntl_licensing_get_info` API has been enhanced to provide the following additional information:

- `appContextInfo` - The information about the various parameters set in an application context.
- `featureCumulativeTrialInfo` - The cumulative information about the trial period of trial licenses for the given feature.

- serverInfo - The information about the License Manager.
- serverPoolInfo - The information about a group of License Managers hosting the same license for high availability.

### **Renaming of Query Type Macros**

In this release, the existing query type macros of the `sntl_licensing_get_info` API are also renamed to reflect their actual use. The following table includes a list of such query types:

<b>Old Query Type (v9.0.0)</b>	<b>Renamed to...(v9.1.0)</b>
SNTL_FEATURE_INFO	SNTL_QUERY_FEATURE_INFO
SNTL_LICENSE_INFO	SNTL_QUERY_LICENSE_INFO
SNTL_CLIENT_INFO	SNTL_QUERY_CLIENT_INFO
SNTL_LIBRARY_INFO	SNTL_QUERY_LIBRARY_INFO
SNTL_RECIPIENT_INFO	SNTL_QUERY_RECIPIENT_INFO
SNTL_FINGERPRINT_INFO	SNTL_QUERY_FINGERPRINT_INFO

### **New XML Response Fields for Existing Query Types**

In this release, new XML response fields have been introduced in the `sntl_licensing_get_info` API, in place of few existing fields to reflect their actual usage. The existing XML fields have been marked as obsolete and will be deprecated in the future releases. The following table includes a list of obsolete XML fields and the corresponding new XML response fields:

<b>Query Type</b>	<b>Existing XML Response Fields (v9.0.0)</b>	<b>New XML Response Fields (v9.1.0)</b>
SNTL_QUERY_FEATURE_INFO	trialDaysCount, trialElapsedHours, trialCalendarPeriodLeft trialElapsedPeriodLeft	trialDays trialSeconds trialDaysLeft, trialSecondsLeft
SNTL_QUERY_LICENSE_INFO	trialDaysCount trialElapsedHours trialCalendarPeriodLeft trialElapsedPeriodLeft	trialDays trialSeconds trialDaysLeft, trialSecondsLeft
SNTL_QUERY_CLIENT_INFO	sharedIdName	vendorDefinedSharingId
	clientVendorUsageData	vendorUsageData
	isSharing	sharedClientCount



**Added New XML Response Fields**

In this release, the following new XML response fields are also introduced:

Query Type	New XML Response Field
SNTL_QUERY_FEATURE_INFO	commutedFromServer - The License Manager from which the license is obtained for the commute action.
SNTL_QUERY_LICENSE_INFO	activationBirthTime - The entitlement start time (epoch time). activationExpiryTime - The entitlement expiration time (epoch time).

**Enhancement in the `sntl_licensing_get_session_info` API**

In this release, a new XML field `refreshStatus` is added to the output of the `sntl_licensing_get_session_info` API to inform about the current status of the refresh process.

**Renaming of Attribute Key Names**

In this release, few attribute keys are renamed to reflect their actual use. The following table includes a list of such attributes:

API	Old Attribute Key (v9.0.0)	Renamed to...(v9.1.0)
<code>sntl_licensing_login_attr</code>	<code>SNTL_ATTR_LOGIN_VENDOR_IDENTIFIER</code>	<code>SNTL_ATTR_LOGIN_VENDOR_ISOLATION_IDENTIFIER</code>
<code>sntl_licensing_logout_attr</code>	<code>SNTL_ATTR_LOGOUT_UNITS_CONSUMED</code>	<code>SNTL_ATTR_LOGOUT_UNITS_TO_RELEASE</code>
<code>sntl_licensing_login_attr</code>	<code>SNTL_ATTR_LOGIN_CHALLENGE_SIZE</code>	This attribute has been removed
<code>sntl_licensing_refresh_attr</code>	<code>SNTL_ATTR_REFRESH_CHALLENGE_SIZE</code>	This attribute has been removed

## Traditional API Enhancements

The following major enhancements, related to the Traditional API, are included in this release. For more information, refer to the Sentinel RMS SDK API Reference Guide:

### *Obtaining the Start and Expiration Time of a Checked-out Commuter License*

Starting v9.1.0, you can obtain the start and expiration time of a checked-out commuter license, in hours and minutes. To support this enhancement, the following changes are made:

- The following additional fields are introduced in the *VLScommuterInfo* structure:
  - `structSz`
  - `birth_hours`
  - `birth_minutes`
  - `death_hours`
  - `death_minutes`
- Introduced the *VLSgetCommuterInfoExt* API, an extension of the *VLSgetCommuterInfo* API, to obtain the start and expiration time of a checked-out commuter license.



Developers using the Unified API, can use the Unified API `sntl_licensing_get_info()` with query type `featureInfo` and `licenseInfo`, to retrieve the commuter information. Make sure to have set the contact server as "no-net"

## Licenses with Entitlement Start and Expiration Time

Starting v9.1.0, licenses generated include the entitlement start and expiration time values (epoch time), useful for SCL Add-on for RMS customers.

To support this enhancement, the following updates are also made:

### *New Fields in the CodeT (License), VLSfeatureInfo and VLSlicenseInfo structures*

The following fields are added in the CodeT (RMS License Structure), *VLSfeatureInfo* and *VLSlicenseInfo* structures:

- `activation_birth_time`
- `activation_expiry_time`

For more information, refer to the Sentinel RMS SDK License Generation API Reference Guide and Sentinel RMS SDK API Reference Guide.



You can retrieve the value of the new fields using the *VLSgetFeatureInfo*, *VLSgetLicenseInfo* and `sntl_licensing_get_info` APIs.

### *License Version Upgraded to v17*

Due to updates in the license structure, the license version has been upgraded to v17.

## Enhancements in the Java Interface for Unified API

In this release, the Java interface for Unified APIs is also updated to reflect the following enhancements:

- The Unified API enhancements listed in the section "**Unified API Enhancements**".
- Renamed the Java interface installation directory from *Java* to *java-jna*.

## Miscellaneous Changes

In this release, the following changes are also included:

### *Increased Size of Vendor Usage Data*

The length of Vendor Usage Data has been increased from 100 to 255 bytes. This information will be reflected in the Raw usage data report of the Sentinel EMS. For more information, see the Sentinel EMS User's Guide.

### *Documentation Changes*

In this release, the following major documentation changes are also included:

#### ***Separate Document for the License Generation API***

Starting version 9.1.0, the License Generation API are moved *from* the API Reference Guide *to* the Sentinel RMS License Generation API Reference Guide. Prior to this release, these API were included in the Sentinel RMS SDK API Reference Guide. The document is available in the PDF format only, under the Sentinel RMS SDK SDK installation.

#### ***Removal of the HTML-based Help in the SDK***

The HTML-based Help for the following documents is no longer included in the RMS SDK. Instead, use of the hosted Online Help is recommended.

- Sentinel RMS SDK API Reference Guide
- Sentinel RMS SDK Developer's Guide

#### ***HTML 5 based Online Help***

The Online Help is in the HTML 5 format and offers the following advantages:

- Full topic URLs for better link sharing: In HTML5 Help, each topic has a unique URL so they can be shared, emailed or saved in the browsers bookmarks easily.
- Better search results and display: In HTML5 output, the search feature is included in a search bar above the topics. This is in contrast to the previous Help which displayed the Search option in an accordion or tab in the left-side of the page. Furthermore, the Search output offers Google-style search results and display. An example of the HTML5 based Help is shown here: <http://sentinelrms.safenet-inc.com/scl/>

## What's New in the SCL Add-on for RMS?

SCL Add on for RMS v9.1 includes the following major enhancements. To learn more about them, refer to its Release Notes and *SCL Add-on for RMS Overview Guide*:

- **Introduced Cloud Served – Connected License Deployment Mode**  
In addition to the *on-premise* and *Cloud Served - Lease* deployment modes, the *Cloud Served - Connected* deployment is now also supported. This mode is primarily meant for hosted and / or always connected applications to leverage the benefits of cloud licensing.
- **Support for Named User Licensing**  
For *Cloud Served - Connected* deployment, Named User Licensing is also supported. It allows ISVs to create licenses that can be consumed only by specific users or entities.
- **Support for Usage Count Multiplier**  
Usually, each licensing session consumes one count per a login-logout call sequence. At times, when vendor wants to represent this consumption differently, then a usage count multiplier value can be specified, both at the start of the session (login) and / or at its end (logout).
- **Support for Peak Concurrency**  
Peak Concurrency obtains usage statistics about the maximum number of concurrent sessions achieved during a given period.
- **Redundant License Manager Support for Lease Licenses**  
The License Managers in the *Cloud Served - Lease* deployment mode can now be configured in redundant fashion to provide high-availability when the primary License Manager goes down.

## Problems Corrected in This Release

In this release, the following problems are corrected:

User Story / Service Request ID	Problem Description
RMS-6320	After revocation, the aggregate license seat count changes to no limit.
RMS-6321	The license sharing is not working properly when hold time is specified.
RMS-6369	Modify the description of the VLSgetFeatureInfo (num_licenses field).
RMS-6466	The License Generator cannot generate a demo license that expires beyond 31 Dec 2016.
RMS-6590	The VLSsetTimeoutInterval() API is unable to handle timeout interval value of less than 3 seconds correctly.
RMS-6877	The VLSGetFeatureInfo API is returning unexpected results after upgrading the RMS version.
RMS-6912	Documentation update related to VLSrevokeByPermissionTicket API.
RMS-7062	The VLSgetTrialUsageInfo API should include information about the frequency of trial usage data refresh.
RMS-7095	The lscgen - Command-Line Options document specified incorrect format of the locking information of the redundant License Managers.
RMS-7272	Solved the linking issues of the static RMS 9.0 libraries when used with the shared flag.
RMS-7325	Correct the description of the sntl_licensing_login_attr API.
RMS-7412	Not able to recompile the application with the static libraries of RMS 9.0 Linux SDK.

## Installation Information

---

This section contains following information about installation of the product:

- "Before You Install..." on page 15
- "System Requirements" on page 16
- "Installation Instructions" on page 18
- "Installed Directories" on page 20

## **Before You Install...**

Before you begin installing the RMS SDK, note the following:

### ***Administrator Privileges***

You must have Administrator privileges to successfully install all the components.

### ***RMS SDK Serial Number***

You require a valid serial number provided by Gemalto. The installer prompts you to enter the serial number specific to you.

## System Requirements

To use the Sentinel RMS SDK, the minimum hardware and software requirements are:

Hardware Requirements	Software Requirements
<p><b>Processors:</b></p> <ul style="list-style-type: none"> <li>■ x86 processors for 32-bit</li> <li>■ x86-64 processors for 64-bit</li> </ul>	<p><b>Operating Systems and Compilers:</b></p> <p>Red Hat Enterprise Linux 6.x (Kernel v2.6.32)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.4.7</li> <li>■ glibc v2.12</li> </ul> <p>Red Hat Enterprise Linux 7.x (Kernel v3.10.0-121)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.8.2 20140120</li> <li>■ glibc v2.17</li> </ul> <p>SUSE Linux Enterprise Server 11 SP4 (Kernel v2.6.18)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.1.2</li> <li>■ glibc v2.4</li> </ul> <p>SUSE Linux Enterprise Server 12 (Kernel v3.0.13)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.3.4</li> <li>■ glibc v2.11.3</li> </ul> <p>Open SUSE 13.1 (Kernel v3.11.6)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.8.1</li> <li>■ glibc v2.18</li> </ul> <p>Open SUSE 13.2 (Kernel v3.7.10)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.7.2</li> <li>■ glibc v2.17</li> </ul> <p>Ubuntu 15.x (Kernel v3.1.0)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.8.2</li> <li>■ glibc v2.13</li> </ul> <p>Ubuntu 16.x</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.8.2</li> <li>■ glibc v2.13</li> </ul> <p>Debian Linux 7.x (Kernel v2.6.32)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.4.5</li> <li>■ glibc v2.11.2</li> </ul> <p>Debian Linux 8.x (Kernel v3.2.0.4)</p> <ul style="list-style-type: none"> <li>■ gcc (32 and 64-bit) v4.7.2</li> <li>■ glibc v2.13</li> </ul>
<p><b>Monitor and Settings:</b> VGA monitor with 800 x 600 resolution (1024 x 768 recommended)</p>	<p><b>Java Runtime Environment:</b> Java Runtime Environment v1.6, 1.7 and 1.8 for the Java interface.</p>
<p><b>Hard Disk Space:</b></p>	<p><b>Web Browser (for viewing HTML Helps):</b></p>



Hardware Requirements	Software Requirements
200 MB free hard disk space	Firefox 3.5 or later
<b>RAM:</b> 128 MB RAM	<b>PDF File Viewer (for viewing PDF documents):</b> Adobe Acrobat 4.0 (or later)
<b>Peripherals:</b> <ul style="list-style-type: none"><li>■ A USB port or a parallel port to attach the license meter key. This is required on the system where licenses are to be generated.</li></ul>	

## Installation Instructions

1. The Software is packed in a .tar archive. Extract files from the archive as follows:

```
tar -xvf RMSSDK9.1.0.0104Linux.tar
```

2. Change the directory where the installation script *install.sh* exists (*slm\_0900\_linux\_combo\_cdrom* directory). Afterward, type *sh install.sh* to start the installation.
3. Accept the license agreement to proceed with the installation.
4. Enter the path of the installation directory.
5. You will be required to specify the RMS SDK serial number—included with the product packaging—to complete the installation.



Sentinel RMS is self-contained in the installation directory. To uninstall, remove the directory. Do stop the Sentinel RMS License Manager before uninstalling.

## Installing Sentinel UNIX Driver (SUD)

Sentinel UNIX Driver (SUD) needs to be installed for making use of the hardware keys (for CID based locking and license generation). To install SUD on your system:



The RMS License Manager included with this release supports version 7.5.0 of the Sentinel UNIX Driver. On Linux 32-bit, both USB and parallel drivers are provided. On Linux 64-bit, only USB driver is provided.

1. Extract the SUD installer from its compressed tar image placed at *<installdir>/re-distributable/licenseManager/SUDInstaller.tar.gz* location on the DVD by giving the following command:


```
tar -xvzf SUDInstaller.tar.gz
```

2. Change directory to SUDInstaller.
3. To install SUD parallel driver on kernel version 2.4.x:
  - Change directory to *parallel/2.4.x*.
  - Run command *rpm -i --force sntl-sud-parallel-7.1.0-0.i386.rpm* to install the driver.
4. To install SUD parallel driver on kernel version 2.6.x:
  - Change directory to *parallel/2.6.x*.
  - Run command *rpm -i --force sntl-sud-paralleldrv-7.1.3-0.i386.rpm* to install the driver.
5. To install SUD USB driver (applicable to both 32-bit and 64-bit):

- Change directory to USB.
- Run command `rpm -i --force sntl-sud-7.5.0-0.i386.rpm` to install the driver.

## Installed Directories

The following directories are installed:

Directory or File	Description
<b>development</b>	Contains all the RMS libraries, header files, and source code for licensing and customization purpose.
<b>manuals</b>	Documentation for the Sentinel RMS SDK.
<b>samples</b>	Examples that illustrate the various features of Sentinel RMS. The include files, which provide the prototypes for various Sentinel RMS library functions.
<b>vendorTools</b>	<p>Contains the utilities and files for your use.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  The license generator is no longer included with the SDK. A download link is provided to you using e-mail. If not, contact <b>Technical Support</b> for obtaining it.         </div>
<b>redistributable</b>	The utilities and files for your customers, including the Sentinel RMS License Manager installer.
<b>ReleaseNotes.pdf</b>	This file.

## Major Documentation Resources

---

This section provides details about the major documentation resources for the product:

### Developer's Guide

Contains the complete product overview, the necessary information for licensing and distributing the applications. Useful for developers planning and implementing licensing. To access, use the following ways:

- PDF version is installed on the system can be accessed using the Doc Access Page (.htm) in the *Manuals* directory.
- The latest online copy can be accessed here:  
<http://sentinelrms.safenet-inc.com/RMSDocumentation/Vendor/Default.htm>

### API Reference Guide

Contains details about all the API functions, including the licensing library, system initialization, and so on. Useful for developers integrating the API functions in the code. To access, use the following ways:

- PDF version is installed on the system can be accessed using the Doc Access Page (.htm) in the *Manuals* directory.
- The latest online copy can be accessed here:  
<http://sentinelrms.safenet-inc.com/RMSDocumentation/Vendor/Default.htm>



The Developer's Guide and API Reference Guide are bundled together as the Vendor's documentation. You can find it as the last item in its ToC (in the left-side pane).

### System Administrator's Guide

Contains details about using the system administration and License Manager configuration options. Useful for the System Administrator of the end user (on the customer site). To access, use the following ways:

- The HTML version installed on the system can be accessed using the Doc Access Page (.htm) in the *Manuals* directory.
- The latest online copy can be accessed here:  
<http://sentinelrms.safenet-inc.com/RMSDocumentation/SysAdmin/Default.htm>

### License Generation API Reference Guide

Contains details about the License Generation API functions. The PDF version is installed on the system in the *Manuals* directory.

## SCL Add on for RMS Documentation

The complete documentation of the SCL Add on for RMS is hosted at: <http://sentinelrms.safenet-inc.com/scl/>

For getting started, begin with the *SCL Add-on for RMS Overview Guide*.

## Technical Support

---

You can contact us using any of the following options:

- **Business Contacts** - To find the nearest office or distributor, use the following URL:  
<https://sentinel.gemalto.com/contact-us-sm/>
- **Technical Support** - To obtain assistance in using Gemalto Sentinel products, feel free to contact our Technical Support team:
  - Phone: 800-545-6608 (US toll free), +1-410-931-7520 (International)
  - Regional Support Contact Information: <https://sentinel.gemalto.com/technical-support-sm/>
  - E-mail: [support@safenet-inc.com](mailto:support@safenet-inc.com)
  - URL: <https://sentinel.gemalto.com/technical-support-sm/>
- **Downloads** - You may want to check out updated installers and other components here:  
<https://sentinel.gemalto.com/technical-support-sm/>